

PRISM Software Download Information

NOTE: USERS OF ZONEVIEW PLUS SOFTWARE

It is recommended that you DO NOT UNINSTALL ZoneView Plus Software before installing the new PRISM Software. PRISM can co-exist with ZoneView Plus software. All setpoints & schedules will be maintained when you install the new PRISM software. You can also copy all log files, custom screen files, unit descriptions etc., from ZoneView Plus to PRISM. To migrate the ZoneView Plus files to PRISM copy all files with the extensions; CFG, DAT, ALM, SPT, BMP, WMF, GIF and SCR from the ZoneView Plus directory to the directory PRISM has been installed in.

Another reason to leave ZoneView Plus on the computer until PRISM is configured is to insure that should you have an installation problem or glitch, you will still be able to use the existing ZoneView Plus software to access your system until PRISM can be properly installed.

DOWNLOADING AND INSTALLATION INSTRUCTIONS

Download the file from the website to any directory on your computers hard drive. Open Windows Explorer and locate the file you just downloaded. Highlight and double click the file you just downloaded. This will initiate the self extraction utility. The default directory that the file will be extracted to is C:\TEMP\PRISM. If desired you can select any directory you wish by typing in that directory path on the extraction utility "extract to directory" box.

At this point be sure that no other programs are running on your computer. This is very important!!!!!! If other programs are running, the program may not install properly. This includes virus protection programs or other TSR programs that may be running in the background. Using Windows Explorer, go to the C:\TEMP\PRISM directory or the directory you chose to extract the PRISM software file into. Highlight and double click the setup.exe file. Follow the directions on the screen to complete the installation.

IMPORTANT!!!!!!

By default the PRISM software installation program will install the PRISM program to the directory "C:\PRISM. If you are going to use the custom screen editor program functions of PRISM, do not change the installation directory during the initial installation or the custom screen editor will not function properly.

If for any reason this program does not install or doesn't run after installation, it must be uninstalled using "Add/Remove Programs" located in the Windows 95/98/ME/2000/XP Control Panel folder before attempting to re-install it to your computer.

TECHNICAL SUPPORT:

If you have problems with the program installation or are unsure about how to install the program you can call WattMaster Controls at 816-505-1100 and ask for Technical Support.